OpenCV Python

Linux Installation Manual



Version 1.7 e-con Systems 04/02/2025



Disclaimer

e-con Systems reserves the right to edit/modify this document without any prior intimation of whatsoever.



Contents

INTRODUCTION TO OPENCV	3
Prerequisites	3
DESCRIPTION	3
BUILDING OPENCV	4
BOLDING OF ENCY	
STEP 1 - INSTALLING DEPENDENCIES	4
STEP 2 - CONFIGURING OPENCV	5
BUILDING SAMPLE CODE	7
USING PREBUILT BINARY	8
TROUBLESHOOTING	9
SUPPORT	13



Introduction to OpenCV

Open Source Computer Vision Library (OpenCV) is an open source computer vision and machine learning software library. OpenCV libraries are used to communicate with Cameras. APIs introduced in the OpenCV can be supported with all e-Con systems cameras.

This document helps to install the OpenCV in Linux and build a sample code to access the camera with OpenCV.

Prerequisites

The prerequisites are as follows:

- Download OpenCV from here (https://github.com/opencv/opencv)
- Or download the official OpenCV release using wget :

```
$ cd ~
$ wget -0 opencv.zip \
https://github.com/opencv/opencv/archive/4.7.0.zip
```

- Download OpenCV contrib from here (https://github.com/opencv/opencv contrib)
- Or download the official OpenCV contrib release using wget :

```
$ wget -O opencv_contrib.zip \
https://github.com/opencv/opencv_contrib/archive/4.7.0.zi
p
```

Unzip the archieves

```
$ unzip opencv_contrib.zip
```

- GCC 4.4.
- CMake 2.8.7 or higher.
- GTK+2.x or higher, including headers (libgtk2.0-dev).
- Python 3.6.9
- Library packages: libjpeg-dev, libpng-dev, libtiff-dev, libjasper-dev, libavcodec-dev, libavformat-dev, libswscale-dev, libv4l-dev, libxvidcore-dev, libx264-dev, libgtk-3-dev, libatlas-base-dev, gfortran.

Description

The following steps have been tested on Ubuntu 20.04 and with Python 3.8.10. OpenCV must work on any other relatively modern version of Linux OS.



The OpenCV is a sample command line application used to demonstrate some of the features of the e-con Cameras with OpenCV APIs. The steps to build OpenCV are as follows:

Step 1. <u>Installing Dependencies</u>

Step 2. Configuring OpenCV

Step 1 - Installing Dependencies

The below table lists the dependencies to be installed for using OpenCV.

Table 1: Installing Dependencies

Dependencies	Commands	
Some general development libraries	<pre>\$ sudo apt-get install build- essential make cmake cmake-qt-gui g++ unzip pkg-config</pre>	
Video4Linux Camera development libraries	<pre>\$ sudo apt-get install libv4l-dev</pre>	
OpenGL development libraries for creating graphical windows	\$ sudo apt-get install libglew-dev	
GTK development libraries for creating graphical windows	\$ sudo apt-get install libgtk-3-dev	
Udev development libraries for accessing device information	\$ sudo apt-get install libudev-dev	
Libav video input or output development libraries	\$ sudo apt-get install libavformat- dev libavutil-dev libswscale-dev libavcodec-dev libavcodec-extra libdc1394-* libjpeg-dev libpng-dev libtiff-dev libopencv-dev libxvidcore-dev libx264-dev libopencv-dev	
Eigen3 math development libraries	<pre>\$ sudo apt-get install libeigen3-dev</pre>	
Python 3 headers and libraries	\$ sudo apt-get install python3.6-dev	
Pyudev library	\$ sudo python3 -m pip install pyudev	
Numpy library	\$sudo apt-get install python3-numpy	



In Ubuntu, the dependency libraries varies.

Based on the Ubuntu versions, the development libraries will differ, for example in ubuntu 18.04 libavcodec version will be 57. Thus, install dependencies which supports the ubuntu versions.

For 20.04 OS, extra dependencies are needed. They include: pkg-config, gfortran, openexr, libatlas-base-dev, libtbb2, libopenexr-dev, libgstreamer-plugins-base1.0-dev, libgstreamer1.0-dev

For 18.04 Os: libavcodec-extra57, pkg-config, libavformat57, libavutil55

Step 2 - Configuring OpenCV

The steps to configure OpenCV are as follows:

- Replace the videoio folder inside the downloaded /opencv-4.7.0/modules directory with the folder provided by e-con Systems in this link (https://github.com/econsystems/opencv/tree/master/Source)
- 2. To build and install OpenCV, go to the downloaded opency-4.7.0 directory.

```
$ mkdir release
$ cd release
$ cmake -D CMAKE BUILD TYPE=RELEASE \
    -D CMAKE INSTALL PREFIX=/usr/local \
    -D BUILD opencv python3=ON \
    -D BUILD opencv world=ON \
    -D WITH CUDA=OFF \
    -D INSTALL PYTHON EXAMPLES=ON \
    -D OPENCV EXTRA MODULES PATH=~/<opencv contrib-
4.5.5/modules \
    -D OPENCV ENABLE NONFREE=ON \
    -D OPENCV GENERATE PKGCONFIG=ON \
    -D BUILD EXAMPLES=ON \
    -D WITH GPHOTO2=OFF \
    -D BUILD TESTS=OFF \
    -D WITH VTK=OFF \
    -D WITH GSTREAMER=OFF \
    -D BUILD PERF TESTS=OFF ..
```

3. To build and install the OpenCV libraries in the location /usr/local/lib/, you must run the following commands.

```
$ sudo make -j4 && sudo make install
```



4. Install OpenCV Python

\$ sudo pip3 install opency-python==4.7.0.68

5. Copy the 'cv2' folder from the '/usr/local/lib/<python_version>/site-packages' directory to the '/usr/local/lib/<python_version>/dist-packages' directory. Example:

For Ubuntu 18.04, python version 3.6 For Ubuntu 20.04, python version 3.8



Building Sample Code

This section describes about how to build the sample code.

The steps to run sample application are as follows:

- 1. Download OpenCV Python sample command line application from here (https://github.com/econsystems/opency/tree/master/Source).
- 2. To run the sample code, run the following command.

```
$ sudo python3 main.py
```

3. Number of devices connected to the PC will be displayed just as below shown.



Using Prebuilt binary

This section describes about how to build the sample code.

The steps to run sample application are as follows:

- 1. Download OpenCV Python Application package from here (https://github.com/econsystems/opencv/tree/master/Source).
- 2. Go to the source folder.
- 3. To run the sample code, run the following command.

```
$ sudo PYTHONPATH="@path/cv2/"
LD_LIBRARY_PATH="@path/lib" python3 main.py
```

```
*eg:setting cv2 path /Binary/<Opencv_4.7.0>/Linux/<18.04_x64 or 20.04_x64>/cv2/
```

- *eg:setting lib path Binary/<Opencv_4.7.0>/Linux/<18.04_x64 or 20.04_x64>/lib
- 4. Number of devices connected to the PC will be displayed just as below shown.



Troubleshooting

In this section, you can view the list of commonly occurring issues and their troubleshooting steps.

Camera Device connected, but the application does not displayed.

It seems like the camera is not properly detected by Linux, so check with the path cd /sys/class/video4linux/ to detect the device.

CMake Error: The source directory does not appear to contain CMakeLists.txt.

- 1. Run cmake-gui from the terminal.
- 2. Provide the source and release folder path of the OpenCV project.
- 3. Configure and generate the solution.

Compiling command line application, libudev.so error adding symbols, DSO missing from command line.

Include the ludev dependency in the compilation command.

```
Eg: CMAKE CXX FLAGS="-ludev"
```

Camera displays in the command line but selecting the index does not end up with the preview.

Make sure the camera connected to the port starts with video0 /sys/class/video4linux.

PermissionError: [Errno 13] Permission denied: '/dev/hidraw'.

Provide sudo permission to the command.

```
sudo python3 main.py
```



In Ubuntu, the dependency libraries varies.

Based on the Ubuntu versions, the development libraries will differ, for example in ubuntu 16.04, libavcodec version will be 56, but in ubuntu 18.04 libavcodec version will be 57. Thus, install dependencies which supports the ubuntu versions.

For 20.04 OS, extra dependencies are needed. They include:

pkg-config, gfortran, openexr, libatlas-base-dev, libtbb2, libopenexr-dev, libgstreamer-plugins-base1.0-dev, libgstreamer1.0-dev

For 18.04 Os: libavcodec-extra57 pkg-config libavformat57 libavutil55

For 16.40s: libavcodec-ffmpeg-extra56 libavformat-ffmpeg56 libavutil-ffmpeg54 libswscale-ffmpeg3

Error loading libopencv_world.so

```
sudo LD_LIBRARY_PATH=<path_to_the_libopencv_world.so>
python3 main.py
```

Instead, if you wish to add the path to libopencv_world.so, permanently to the library path. Go to /etc/ld.so.conf.d/. Create a config file named opencv.conf, mention the path inside the config file and give the command:

```
$ sudo ldconfig
```

ModuleNotFoundError: No module named 'cv2'

```
ramprasath@ramprasath:~/PycharmProjects/opencv_python$ python main.py
Traceback (most recent call last):
   File "main.py", line 4, in <module>
        import display
   File "/home/ramprasath/PycharmProjects/opencv_python/display.py", line 3, in <module>
        import cv2
ModuleNotFoundError: No module named 'cv2'
ramprasath@ramprasath:~/PycharmProjects/opencv_python$
```

Step 1: Be sure to check the site-packages (and even dist-packages) directory for the system install of Python located in /usr/local/lib/python3.6/site-packages/. Make sure (1) there is a cv2.so file in the site-packages directory and (2) its properly symlinked to a valid file.

Step 2: If the cv2.so file is not present, check in your build/lib directory of your OpenCV build. There should be a cv2.so file there (if both cmake and make executed without error). If the cv2.so file is present, manually copy it into both the system site-packages (or dist-packages) directory.



AttributeError: 'cv2.VideoCapture' object has no attribute 'getDevices'

This error may come if you installed opency previously without the e-consystems videoio module and the current build and install is not successful. Check in your build/lib directory of your OpenCV build. There should be a cv2.so file there (if both cmake and make executed without error). If the cv2.so file is present, manually copy it into both the system site-packages (or dist-packages) directory.

Then run the following command.

```
$ sudo PYTHONPATH="@build/lib/python3"
LD LIBRARY PATH="@build/lib" python3 main.py
```

Undefined reference to main:

replace videoio module freshly, delete opency folders present in

/usr/local/include/

Rebuild opency again. If problem still exist uncheck OpenCL, gstreamer and opency test flags

If cv2 module was not builded:

- 1.Run cmake-gui in terminal
- 2. Provide the source and release folder path of the OpenCV project.
- 3. Search for python



4. Edit variabels as shown below

BUILD_opencv_python3

BUILD_opencv_python_bindings_generator
V
INSTALL_PYTHON_EXAMPLES
OPENCV_FORCE_PYTHON_LIBS
PYTHON2_EXECUTABLE
PYTHON2_INCLUDE_DIR
PYTHON2_INCLUDE_DIR
PYTHON2_LIBRARY
PYTHON3_LIBRARY
PYTHON3_EXECUTABLE
Vusr/bin/python3
PYTHON3_INCLUDE_DIR
PYTHON3_INCLUDE_DIR
PYTHON3_INCLUDE_DIR
PYTHON3_LIBRARY
PYTHON3_NUMPY_INCLUDE_DIRS
PYTHON3_PACKAGES_PATH
lib/python3.6/dist-packages
PYTHON3_PACKAGES_PATH
lib/python3.6/dist-packages



Support

Contact Us

If you need any support on OpenCV sample application, please contact us using the Live Chat option available on our website - https://www.e-consystems.com/

Creating a Ticket

If you need to create a ticket for any type of issue, please visit the ticketing page on our website - https://www.e-consystems.com/create-ticket.asp

RMA

To know about our Return Material Authorization (RMA) policy, please visit the RMA Policy page on our website - https://www.e-consystems.com/RMA-Policy.asp

General Product Warranty Terms

To know about our General Product Warranty Terms, please visit the General Warranty Terms page on our website - https://www.e-consystems.com/warranty.asp



Revision History

Rev	Date	Description	Author
1.0	19-May-2020	Initial Draft	Ramson Jehu K
1.1	29-July-2020	Added changes	M Vishnu Murali
1.2	15-August-2020	Added changes	Murali Mohan M
1.3	08-Sep-2020	Added few points in troubleshooting	M Vishnu Murali
1.4	29-July-2022	Updated document for 4.5.5 version	Nivedha Janarthanan
1.5	14-September-2023	Updated document for 4.6.0 version	Sushanth S
1.6	06-November-2023	Updated document for 4.7.0 version	Sushanth S
1.7	02-April-2025	Updated the dependencies for installing in Linux OS	Adithya T S